## Standard Header (COMX <-> PC)

| Address | Bytes | Address<br>Description | Value     | Value Description                           |
|---------|-------|------------------------|-----------|---|
| 0h      | 1     | Command type           | 0         | None  |
|         |       | J                      | 1         | Save  |
|         |       |                        | 2         | Load  |
|         |       |                        | 3         | Get first CAT content                       |
|         |       |                        | 4         | Get next CAT content                        |
|         |       |                        | 5         | CD - Change directory                       |
|         |       |                        | 6         | MKDIR                                       |
|         |       |                        | 7         | RMDIR                                       |
|         |       |                        | 8         | DEL   |
|         |       |                        | 9         | Fetch time & date                           |
|         |       |                        | 12h, 14h, | Used in image header                        |
|         |       |                        | 16h, 1Ah  |   |
|         |       |                        | 18h       | COMP, Compare files                         |
|         |       |                        | 19h       | URL   |
|         |       |                        | 42h       | DLOAD                                       |
|         |       |                        | 81h       | Save and overwrite existing file            |
|         |       |                        | 82h       | Load continue                               |
|         |       |                        | FFh       | Cancel command                              |
| 1h      | 18    | Program or             |           | Name in ASCII characters                    |
|         |       | directory name         |           |   |
| 13h     | 1     | Result                 | 0         | File found                                  |
|         |       |                        | ADh, AEh, | Used in image header                        |
|         |       |                        | AFh       |   |
|         |       |                        | F3h       | URL not found                               |
|         |       |                        | F4h       | No more data found                          |
|         |       |                        | F5h       | Server error                                |
|         |       |                        | F6h       | Network error                               |
|         |       |                        | F7h       | File open                                   |
|         |       |                        | F8h       | File error                                  |
|         |       |                        | F9h       | File size > 8K                              |
|         |       |                        | FAh       | File size > 64K                             |
|         |       |                        | FBh       | File size < 8K                              |
|         |       |                        | FCh       | File size < 64K                             |
|         |       |                        | FDh       | File type error                             |
|         |       |                        | FEh       | Address error                               |
|         |       |                        | FFh       | File NOT found                              |
| 14h     | 2     | Actual file            |           |   |
|         |       | length (excl.          |           |   |
|         |       | header)                |           |   |
| 16h     | 1     | Program type           | 1         | .comx machine code                          |
|         |       |                        | 2         | .comx 'old' regular save/load (for backward |
|         |       |                        |           | compatibility reasons only)                 |

|     |    |                      | 3        | .comx F&M basic sa             | ave/load           |               |
|-----|----|----------------------|----------|--------------------------------|--------------------|---------------|
|     |    |                      | 4        | .comx 'old' and inco           |                    | a load (for   |
|     |    |                      | '        | backward compatib              | J                  | •             |
|     |    |                      | 5        | .comx regular data             | ,                  | /             |
|     |    |                      | 6        | .comx regular save             |                    |               |
|     |    |                      | 7h to 9h | reserved for .comx             |                    |               |
|     |    |                      | 10h      | .bin                           |                    |               |
|     |    |                      | 11h      | .txt (memory dump              | ))                 |               |
|     |    |                      | 12h      | .img                           | •                  |               |
|     |    |                      | 13h      | .ram                           |                    |               |
|     |    |                      | 14h      | .bin, .txt, img, .ram          | , .comx            |               |
|     |    |                      | 20h      | .comx.bak                      |                    |               |
|     |    |                      | 21h      | NVSAVE / nvram.bi              | n                  |               |
|     |    |                      | 22h      | SYSSAVE / system.b             | oin                |               |
|     |    |                      | 23h      | NVSYNC                         |                    |               |
|     |    |                      | 24h      | URL                            |                    |               |
|     |    |                      | 25h      | URL INPUT                      |                    |               |
|     |    |                      | 30h      | .bin.bak                       |                    |               |
|     |    |                      | 31h      | .txt.bak                       |                    |               |
|     |    |                      | 32h      | .img.bak                       |                    |               |
|     |    |                      | 33h      | .ram.bak                       |                    |               |
|     |    |                      | 34h      | .bin.bak, .txt.bak, ir         | ng.bak, .ram.bak,  | .comx.bak     |
|     |    |                      | b7 = 1   | BLOAD/BSAVE activ              |                    |               |
|     |    |                      |          | Basic                          | Machine code       | Data          |
| 17h | 2  | Start address        |          | DEFUS                          | Start              | String        |
| 19h | 2  | End address          |          | EOP                            | End-1              | Array         |
| 1Bh | 2  | Exec address         |          | String/Array/EOD               | Exec               | EOD           |
| 1Ch | 18 | Filename 2           |          | Name in ASCII char             | acters (used for U | SB COMP)      |
| 2Fh | 1  | Category             |          | Not used                       |                    |               |
| 30h | 1  | Case type            | 1        | Standard COMX ch               | ` ' '              | ,             |
|     |    |                      | 2        | Lower case 'default<br>'SHIFT' |                    |               |
|     |    |                      | 3        | Upper case 'default<br>'SHIFT' |                    |               |
|     |    |                      | 4        | Lower case 'default<br>'SHIFT' | and upper case     | characters on |
| 31h | 1  | High byte start load |          |                                |                    |               |
| 32h | 1  | BLOAD/BSAVE          | 30h      | One RAM Bank x                 |                    |               |
|     | -  | type                 | 31h      | RAM Banks 8 to 15              |                    |               |
|     |    |                      | 32h      | RAM Banks 8 to 15              | Continue           |               |
| 33h | 2  | BLOAD/BSAVE          | 2        | 1 2                            |                    |               |
|     |    | length               |          |                                |                    |               |
| 35h | 3  | FW build             |          | FW build (3 ascii va           | lues)              |               |
|     |    | number               |          | ,                              | •                  |               |

### CD Header (PC -> COMX)

| Address   | Bytes | Address     | Value | Value Description             |
|-----------|-------|-------------|-------|-------------------------------|
|           |       | Description |       |                               |
| 0h        | 1     | Result      | FFh   | Directory not found           |
| 1h        | 126   | Full path   |       | Path name in ASCII characters |
| Last byte | 1     | End code    | 0     |                               |

#### URL,"url" Header (COMX -> PC)

| Address   | Bytes | Address      | Value | Value Description            |
|-----------|-------|--------------|-------|------------------------------|
|           |       | Description  |       |                              |
| 0h        | 1     | Command type | 19h   | USB URL                      |
| 1h        | 126   | URL          |       | URL name in ASCII characters |
| Last byte | 1     | End code     | 0     |                              |

### URL (x) and URLLINK (x) Header (COMX -> PC)

| Address | Bytes | Address       | Value   | Value Description                                     |
|---------|-------|---------------|---------|---|
|         |       | Description   |         |   |
| 0h      | 1     | Command type  | 19h     | USB URL   |
| 1h      | 1     | Command       | < 32    | 0 = Normal USB URL / LINK                             |
|         |       |               |         | 1 = PAGE BACK   |
|         |       |               |         | 2 = GO TO HOME  |
|         |       |               |         | 3 = SET HOME  |
|         |       |               |         | 4 = GO TO BOOKMARK                                    |
|         |       |               |         | 5 = SET BOOKMARK                                      |
|         |       |               |         | 6 = HELP  |
| 2       | 2     | Screen number | 0-65535 | USB URL: Data screen number                           |
| 2       | 1     | Bookmark      | 0-9     | Bookmark number                                       |
| 2       | 1     | Link          | 0-255   | USB URLLINK: New link number, link number 0 = default |
|         |       |               |         | page  |

### CAT Header (PC -> COMX)

| Address | Bytes | Address<br>Description | Value     | Value Description                  |                      |                   |
|---------|-------|------------------------|-----------|------------------------------------|----------------------|-------------------|
| 0h-1Bh  |       | '                      |           | Entry 1 + x                        |                      |                   |
|         |       |                        |           | Every header conta                 | ins 4 directory en   | tries and is send |
|         |       |                        |           | until no more entri                | es are available (e  | ntry number = 0)  |
| 0h      | 1     | Entry number           | 0         | No more entries                    | •                    | · ·               |
|         |       |                        | 1 – FEh   | Directory entry nur                | mber of specified f  | file              |
|         |       |                        | FFh       | Directory name                     |                      |                   |
| 1h      | 18    | Program or             |           | Name in ASCII char                 | acters               |                   |
|         |       | directory name         |           |                                    |                      |                   |
| 13h     | 1     | Result                 | 0         | File found                         |                      |                   |
|         |       |                        | ADh       | Format error SS / S                | D                    |                   |
|         |       |                        | AEh       | Format error SS / D                | D                    |                   |
|         |       |                        | AFh       | Format error DS / S                | SD .                 |                   |
|         |       |                        | F5h - FEh | Used in standard he                | eader                |                   |
|         |       |                        | FFh       | File NOT found                     |                      |                   |
| 14h     | 1     | Size                   | 0 - FFh   | File size if > 255 KB; otherwise 0 |                      |                   |
| 16h     | 1     | Program type           | 1         | .comx machine code                 |                      |                   |
|         |       |                        | 2         | .comx 'old' regular                | save/load (for bad   | ckward            |
|         |       |                        |           | compatibility reaso                | ns only)             |                   |
|         |       |                        | 3         | .comx F&M basic sa                 | ave/load             |                   |
|         |       |                        | 4         | .comx 'old' and ince               |                      |                   |
|         |       |                        |           | backward compatik                  | oility reasons only) | )                 |
|         |       |                        | 5         | .comx regular data                 |                      |                   |
|         |       |                        | 6         | .comx regular save,                |                      |                   |
|         |       |                        | 7h to 9h  | reserved for .comx                 | format               |                   |
|         |       |                        | 10h       | .bin                               |                      |                   |
|         |       |                        | 11h       | .txt (memory dump                  | )                    |                   |
|         |       |                        | 12h       | .img                               |                      |                   |
|         |       |                        | 13h       | .ram                               |                      |                   |
|         |       |                        | 20h       | .bak                               |                      |                   |
|         |       |                        |           | Basic                              | Machine code         | Data              |
| 17h     | 2     | Start address          |           | DEFUS                              | Start                | String            |
| 19h     | 2     | End address            |           | EOP                                | End-1                | Array             |
| 1Bh     | 2     | Exec address           |           | String/Array/EOD                   | Exec                 | EOD               |
| 20h-3Bh |       |                        |           | Entry 2 + x                        |                      |                   |
| 40h-5Bh |       |                        |           | Entry 3 + x                        |                      |                   |
| 60h-7Bh |       |                        |           | Entry 4 + x                        |                      |                   |

# Image file Header (COMX <-> PC)

| Address | Bytes | Address<br>Description | Value     | Value Description  |
|---------|-------|------------------------|-----------|--|
| 0h      |       |                        | 0 – 9     | Used in standard header                                      |
|         | '     | oommana type           | 12h       | Get track image file   |
|         |       |                        | 14h       | Save track image file  |
|         |       |                        | 16h       | Test image file  |
|         |       |                        | 18h       | Used in standard header                                      |
|         |       |                        | 1Ah       | Get track image file continue                                |
|         |       |                        | 42h       | Used in standard header                                      |
|         |       |                        | 81h – 82h | Used in standard header                                      |
|         |       |                        | 94h       | Save track image and overwrite existing file                 |
|         |       |                        | FFh       | Cancel command   |
| 1h      | 18    | Program or             | 1111      | Name in ASCII characters                                     |
| '''     | 10    | directory name         |           | Name in Ason characters                                      |
| 13h     | 1     | Result                 | 0         | File found   |
| 1311    | '     | Result                 | ADh       | Format error SS / SD   |
|         |       |                        | AEh       | Format error SS / DD   |
|         |       |                        | AFh       | Format error DS / SD   |
|         |       |                        | F5h - FEh | Used in standard header                                      |
|         |       |                        | FFh       | File NOT found   |
| 14h     | 1     | Density                | 0         | Single   |
|         |       |                        | 1         | Double   |
| 15h     | 1     | Sides                  | 0         | Single   |
|         |       |                        | 1         | Double   |
| 16h     | 1     | Track type             | 0         | First track  |
|         |       | 31                     | 1         | Second until last -1   |
|         |       |                        | 2         | Last track   |
| 17h     | 1     | Drive & side           | 14H       | Drive 1 & side 1   |
|         |       |                        | 34H       | Drive 1 & side 2   |
|         |       |                        | 18H       | Drive 2 & side 1   |
|         |       |                        | 38H       | Drive 2 & side 2   |
| 18h     | 1     | Track number           | 0 to 34   |  |
| 19h     | 1     | Side                   | 0 or 1    |  |
| 30h     | 1     | Case type              | 1         | Standard COMX characters (upper case 'default')              |
|         |       |                        | 2         | Lower case 'default' standard COMX characters on<br>'SHIFT'  |
|         |       |                        | 3         | Upper case 'default' and lower case characters on<br>'SHIFT' |
|         |       |                        | 4         | Lower case 'default' and upper case characters on<br>'SHIFT' |